



PortShare Pro

Installing PortShare Pro

- Place the PortShare Pro control panel into the Control Panels folder on your disk. If you have the ARA (Apple Remote Access) AND/OR Open Transport software running on this machine, place the PortShare Task background application into the Extensions folder (you do not need this file if ARA is not installed):




- Restart your computer. When the MacOS system loads, PortShare Pro displays its icon on the bottom of the screen.
- To share a device connected to some computer, open the PortShare Pro control panel there, select the serial port to share, click the **Shared** button and give the shared device some network name:




Any number of serial ports can be made shared on each computer.

- To access a shared device from some other computer, open the PortShare Pro control panel on that computer and click the **New** button. Enter the name for the additional port you want to create (let's say Remote Modem) and click the **Create** button:




- When a virtual port is created, you can configure it. The list on the right side of the PortShare Pro control panel shows all the shared devices on your network. Select the device you want to use:



To have simultaneous access to several shared devices, you may want to create several virtual ports.

- Open a communication application on the computer with the virtual port created. Open a communication settings window: it should contain a list or a pop-up menu of the serial ports available. Select the virtual port you have created:



PortShare is a trademark is a trademark of [STALKER SOFTWARE, INC.](http://www.stalker-software.com)

STALKER
SOFTWARE INC.

